

(IDEA) Innovation, Development, Education, & Assessment Information Technology Division

Logging into the Remote Desktop

This documentation gives step-by-step instruction on how to remote into a work desktop computer in order access files and software from an off-site computer.

Note: To use Remote Desktop during telework, your office computer must be on. When leaving campus, restart your computer, but DO NOT shut it down or turn off computer.

Finding your PC Name

1. On your work computer, locate the "In the Type Here" to search bar type in the bottom left hand corner of the screen.



2. Type "About Your PC" and select the "About Your PC" system setting that appears.



3. Find device specifications and locate device name.



4. Make a note of Device Name. You will need it for Remote Desktop Connection.

Downloading the Remote Desktop Client on Off Campus Device

If the VPN client is already downloaded onto your computer, skip ahead to the <u>Accessing the Remote</u> <u>Client</u>" section of the document.

- 1. Access https://vpn.coppin.edu on your personal computer via the Google Chrome web browser.
- 2. Enter Coppin Username and Password.



- 3. Select and download Global Protect agent.
 - For Windows select Download 64bit Global Protect agent for windows users.
 - For Mac select Download 32/64 bit Global Protect agent.
- 4. Click the file in the bottom menu to begin the download.



- 5. Once the Installation menu appears, continuously click NEXT until the installation begins.
- 6. Select CLOSE once the installations shows completed.

Accessing the Remote Client

- 1. After installation, a GlobalProtect Client will appear in the bottom right hand corner of the screen.
- 2. Enter <u>vpn.coppin.edu</u> as the portal address and click Connect.
- 3. Input Coppin username and password.
- 4. Once the client shows connected, you are now ready to remote into your work desktop.



5. In your "Type Here to Search" bar. Type RDP and select Remote Desktop Connection



- 6. Enter your work desktop Device name in the Computer field as shown in the example below.
 - (devicename.coppin.edu)



- 7. Click Connect and your computer will begin to remote into your current work PC.
- 8. When prompted, use the <u>username@coppin.edu</u> format and password to connect.
- 9. Select yes for the secure connection prompt appears for to allow connection.

| Windows Security | × | Nemote Desktop Connection |
|---|---|--|
| Enter your credentials | | The identity of the remote computer cannot be verified. Do want to connect anyway? |
| These credentials will be used to connect to doanderson- wx.coppin.sebu. Anderson, Darrell Password | | The worklo compare cutil on the authoritization date to problems with its sec controllow. They be instable to proceed Certification name Certification name Image in the control and the transformation Image in the control and the transformation Image in the control and the transformation Certificative remove |
| daanderson@coppin.edu | | The following anone ware andountiand while v in on the remote computer's contractions of the second |
| More choices | | Do you want to connect despite these certificat |
| OK Cancel | | Vew certicale |

- 10. The Remote desktop icon can be found below in your taskbar at the bottom of the screen.
- 11. Log into your desktop PC from the remote desktop using your Coppin username and password.
- 12. Once work is done, close the remote desktop client and disconnect from VPN by clicking on the icon in the system tray.

| | H 0 - 0X |
|---|---|
| Remote Desktop Icon VPN Connection Icon | erre - Inguisy - Report - Caste - Remose Dasting Consensor Image: Your remote session will be disconnected |
| L 「 」 「 」 「 」 「 」 、 | Programs on the control computer all control force to use allow you have decontented. You are more not to the control social faite for logging on again. Dent display this message again CK Cancel. |

Reminder: To use Remote Desktop during telework, your office computer must be on. When leaving campus, restart your computer, but DO NOT shut it down or turn off computer.

Upon logging back into your home PC, start from the "<u>Accessing the Remote Client</u>" of this document.